

## Product Information

### Proteasome Activity Fluorometric Assay Kit

#### I. Kit Contents:

Components	K2096-100 100 assays	Cap Color	Part Number
Proteasome Assay Buffer	25 ml	WM	K2096-C-1
Proteasome Substrate (Succ-LLVY-AMC in DMSO)	100 µl	Red	K2096-C-2
Proteasome Inhibitor (MG-132 in DMSO)	100 µl	Blue	K2096-C-3
AMC (1 mM in DMSO)	100 µl	Yellow	A7046
Positive Control	lyophilized	Green	K2096-C-4

#### II. Introduction:

Proteasomes are large protein complex located in nucleus and cytoplasm in all eucaryotes. They degrade and recycles the target protein that been tagged by ubiquitin. The tagged protein is hydrolyzes into 7 - 8 amino acids long peptides that are further degraded. The 20S assembly is the protease structure that has chymotrypsin/trypsin/caspase-like protease activities. This Proteasome Activity Assay utilized the chymotrypsin-like activity with an AMC-tagged peptide substrate that releases free, highly fluorescent AMC in the presence of proteolytic activity. The kit also contains Jurkat Cell lysate as a positive control and MG-132 as proteasome inhibitor. This can differentiate proteasome activity from other protease activities that may also in the samples.

#### III. Storage and Handling:

Store the kit at -20°C, protect from light. Read the entire protocol before performing assay. Avoid repeated freeze/thaw cycles. All samples and the Positive Control should be assayed in duplicate, (once in the absence and once in the presence of the Proteasome Inhibitor). An opaque white microwell plate is recommended. This protocol is designed for use in a 96 well plate. 384-well plates may be used but all reagent amounts should be reduced 5-fold (diluted if necessary). Do not use protease inhibitors during cell lysate preparation.

Proteasome Substrate, Proteasome Inhibitor, AMC Standard: Ready to use as supplied. These DMSO solutions must be warmed to room temperature prior to use to melt frozen DMSO. We recommend warming in a 37°C water bath, pipetting up and down to ensure they are completely melted and mixed before use. Store at -20°C in the dark when not in use.

Positive Control: Reconstitute with 100 µl dH<sub>2</sub>O. If kit will be used multiple times over an extended period of time, aliquot portions and store at -80°C. Keep on ice while in use. Avoid repeated freeze/thaw cycles.

#### IV. Assay Protocol:

1. AMC Preparation: Dilute AMC 100-fold (10 µl + 990 µl dH<sub>2</sub>O) then add 0, 2, 4, 6, 8, 10 µl of AMC to a series of microplate wells. Adjust volume to 100 µl/well with Assay Buffer to generate 0, 20, 40, 60, 80 and 100 pmol per well AMC.
2. Positive Control Preparation: Add 10 µl of the positive control to paired wells. Bring volume to total 100 µl by adding 90 µl of Assay Buffer to each well.

3. Samples: Prepare by homogenizing cells with 0.5 % NP-40 in dH<sub>2</sub>O or PBS. Add up to 50 µl of each cell extract or other proteasome sample to be tested to paired wells. Bring the volume of each well to 100 µl with Assay Buffer. Note: For unknown samples, we suggest doing pilot experiment and testing several doses to ensure the readings are within the Standard Curve range.
4. Inhibitor: Add 1 µl of the Proteasome inhibitor to one of the paired wells, 1 µl of Assay Buffer to the other well, mix.
5. Substrate: Add 1 µl of Proteasome Substrate to all wells, mix, protected from light, mix.
6. Read: Measure kinetics of fluorescence development at Ex/Em = 350/440 nm in a micro-plate reader at 37°C for 30 - 60 min. There is a slight lag and nonlinearity to the kinetics due to the time it takes for the reaction mix to warm up to 37°C. Measurement of the wells which do not contain Proteasome Inhibitor will show total proteolytic activity RFU<sub>1</sub> and the wells containing Proteasome Inhibitor will show non-proteasome activity iRFU<sub>1</sub> at T<sub>1</sub> Measure generated by proteasome activity is  $\Delta \text{RFU} = (\text{RFU}_2 - \text{iRFU}_2) - (\text{RFU}_1 - \text{iRFU}_1)$ .

Note: It is essential to read RFU<sub>1</sub>, iRFU<sub>1</sub>, RFU<sub>2</sub> and iRFU<sub>2</sub> in the linear reaction range. It will be more accurate if you monitor the reaction kinetics as shown in Fig. 1B, then choose T<sub>1</sub> and T<sub>2</sub> in the appropriate linear range. From our experience, initial readings RFU<sub>1</sub> and iRFU<sub>1</sub> should be measured after ~ 20 - 25 min.

7. Calculation: Plot the AMC Curve. Apply the  $\Delta \text{RFU}$  to the AMC Curve to get B pmol of AMC (amount generated between T<sub>1</sub> and T<sub>2</sub> in the reaction wells specifically by proteasome activity).

$$\text{Proteasome Activity} = B / (T_2 - T_1) \times V \times \text{Sample Dilution Factor} = \text{nmol/min/ml} = \text{U/ml}$$

Where: B is the AMC amount from AMC Curve (in pmol),

T<sub>1</sub> is the time of the first reading (RFU<sub>1</sub> and iRFU<sub>1</sub>) (in min),

T<sub>2</sub> is the time of the second reading (RFU<sub>2</sub> and iRFU<sub>2</sub>) (in min),

V is the pretreated sample volume added into the reaction well (in µl).

Proteasome Unit Definition: One unit of proteasome activity is defined as the amount of proteasome which generates 1.0 nmol of AMC per minute at 37°C.




Fig. 1. AMC Curve and Proteasome Activity assay using the kit protocol:

A: AMC curve 0-100 pmole; B: Kinetics of Proteasome Activity assay in the absence ① and presence ② of MG-132 Proteasome inhibitor. Equations represent best fit of lines during the linear portion of the reaction (after ~ 25 min in this case).

### General Troubleshooting Guide:

Problems	Cause	Solution
Assay not working	<ul style="list-style-type: none"> <li>• Use of ice-cold assay buffer</li> <li>• Omission of a step in the protocol</li> <li>• Use of a different 96-well plate</li> </ul>	<ul style="list-style-type: none"> <li>• Assay buffer must be at room temperature</li> <li>• Refer and follow the data sheet precisely</li> <li>• Fluorescence: Black plates ; Luminescence: White plates; Colorimeters: Clear plates</li> </ul>
Samples with erratic readings	<ul style="list-style-type: none"> <li>• Use of an incompatible sample type</li> <li>• Samples prepared in a different buffer</li> </ul>	<ul style="list-style-type: none"> <li>• Refer data sheet for details about incompatible samples</li> <li>• Use the assay buffer provided in the kit or refer data sheet</li> </ul>

	<ul style="list-style-type: none"> <li>• Cell/ tissue samples were not completely homogenized</li> <li>• Samples used after multiple free-thaw cycles</li> <li>• Presence of interfering substance in the sample</li> <li>• Use of old or inappropriately stored samples</li> </ul>	<p>for instructions</p> <ul style="list-style-type: none"> <li>• Use Dounce homogenizer (increase the number of strokes); observe for lysis under microscope</li> <li>• Aliquot and freeze samples if needed to use multiple times</li> <li>• Troubleshoot if needed, deproteinize samples</li> <li>• Use fresh samples or store at correct temperatures till use</li> </ul>
Lower/ Higher readings in Samples and Standards	<ul style="list-style-type: none"> <li>• Improperly thawed components</li> <li>• Use of expired kit or improperly stored reagents</li> <li>• Allowing the reagents to sit for extended times on ice</li> <li>• Incorrect incubation times or temperatures</li> <li>• Incorrect volumes used</li> </ul>	<ul style="list-style-type: none"> <li>• Thaw all components completely and mix gently before use</li> <li>• Always check the expiry date and store the components appropriately</li> <li>• Always thaw and prepare fresh reaction mix before use</li> <li>• Refer data sheet &amp; verify correct incubation times and temperatures</li> <li>• Use calibrated pipettes and aliquot correctly</li> </ul>
Readings do not follow a linear pattern for Standard curve	<ul style="list-style-type: none"> <li>• Use of partially thawed components</li> <li>• Pipetting errors in the standard</li> <li>• Pipetting errors in the reaction mix</li> <li>• Air bubbles formed in well</li> <li>• Standard stock is at an incorrect concentration</li> <li>• Calculation errors</li> <li>• Substituting reagents from older kits/ lots</li> </ul>	<ul style="list-style-type: none"> <li>• Thaw and re-suspend all components before preparing the reaction mix</li> <li>• Avoid pipetting small volumes</li> <li>• Pipette gently against the wall of the tubes</li> <li>• Usually wait ~ 25 min before reading T1 (to get past lag phase)</li> <li>• Always refer the dilutions in the data sheet</li> <li>• Use fresh components from the same kit</li> <li>• Recheck calculations after referring the data sheet</li> </ul>
Unanticipated results	<ul style="list-style-type: none"> <li>• Measured at incorrect wavelength</li> <li>• Samples contain interfering substances</li> <li>• Use of incompatible sample type</li> <li>• Sample readings above/below the linear range</li> </ul>	<ul style="list-style-type: none"> <li>• Check the equipment and the filter setting</li> <li>• Troubleshoot if it interferes with the kit</li> <li>• Refer data sheet to check if sample is compatible with the kit or optimization is needed</li> <li>• Concentrate/ Dilute sample so as to be in the linear range</li> </ul>
<p>Note: The most probable list of causes is under each problem section. Causes/ Solutions may overlap with other problems.</p>		

**For research use only! Not to be used in humans.**

## Our promise

If the product does not perform as described on this datasheet, we will offer a refund or replacement. For more details, please visit <http://www.apexbt.com/> or contact our technical team.

Tel: +1-(832)696-8203

Fax: +1-832-641-3177

Email: [sales@apexbt.com](mailto:sales@apexbt.com)

Tel: +1-832-696-8203; Fax: +1-832-641-3177  
<http://www.apexbt.com/>; Email: [sales@apexbt.com](mailto:sales@apexbt.com).